

RESEARCH OF PARASITES IN STOOL

GRAHAM TEST(cellophane tape)

COLLECTION OF SAMPLES GUIDELINES

1. AVOID USING ANTIDIARRHEA OR LAXATIVE MEDICAMENTS BEFORE THE COLLECTION OF THE SAMPLE.
2. IT WILL BE COLLECTED THE SAME DAYS OF THE COLLECTION OF STOOLS UNLESS OTHERWISE PROVIDED.
3. IT WILL BE CARRIED OUT FIRST THING IN THE MORNING BEFORE THE PATIENTS HAS A WASH OR DEFECATES.
4. REMOVE A PART OF THE TRANSPARENT ADHESIVE TAPE OF THE CRYSTAL (LEAVE TWO CENTIMETERS WITHOUT REMOVING) AND APPLY THE ADHESIVE PART ON THE ANUS LIMITS MAKING A PRESSURE GENTLY.REMOVE THE ADHESIVE PART AFTER A FEW SECONDS AND PUT IT AGAIN ON THE CRYSTAL.

WASH YOUR HANDS WITH SOAP.

PROSTHETIC STUDY

A GUIDELINE FOR SAMPLE COLLECTION

PREVIOUS CONDITIONS

1. YOU MUST NOT BE UNDER ANY ANTIBIOTIC TREATMENT DURING THE THEREE DAYS PREVIOUS TO THE STUDY.
2. URINE MUST BE RETAINED FOR THREE HOURS
3. THREE DAYS OF SEXUAL ABSTINENCE

COLLECTION OF THE NECESSARY SAMPLES:

FIRST URINE (URETHRAL FRACTION):

1. IT MUST BE COLLECTED IN THE PROVIDED CONTAINER WITH A NUMBER 1 WRITTEN ON IT.
2. BEFORE THE MICTURITION, THE SKIN OF THE PREPUCE MUST BE RETRACTED, IN ORDER TO PREVENT IT FROM INTERFERING IN THE URINE STREAM. ONCE THE SKIN IS RETRACTED, THE PENIS MUST BE MASSAGED TWO OR THREE TIMES BY PUTTING ON PRESSURE LIGHTLY, FROM THE BASE TO THE END.
3. AFTER THE MESSAGES, START THE MICTURITION WHILE COLLECTING THE URINE FROM THE FIRST DROP, UNTIL THE CONTAINER IS FILLED TO THE LEVEL OF THE PAINTED LINE.

MEDIUM URINE:

1. AFTER MICTURATING ON CONTAINER NUMBER 1, THE URINATION CONTINUES IN THE TOILET BOWL. APPROXIMATELY AT THE MIDDLE OF THE MICTURITION, THE URINE MUST BE COLLECTED IN CONTAINER NUMBER 2, UNTIL IT IS FILLED TO THE LEVEL MARKED ON IT. THE REST OF THE URINE AND THE FINAL PART OF THE MICTURITION MUST NOT BE COLLECTED.
2. THE MICTURITION CAN NEVER BE ENDED IN THE CONTAINER.

SEMEN:

AFTER THE PREVIOUS STEPS, MASTURBATE IN ORDER TO COLLECT A SEMEN SAMPLE IN CONTAINER NUMBER 3.

SEND THE SAMPLES TO THE LABORATORY NO LATER THAN 30 MINUTES AFTER THE COLLECTION.

1.

MINI PARASEP SF

1. TAKE THE STOOLS IN A CLEAN, DRY CONTAINER (FOR INSTANCE, A POT, A PIECE OF PAPER OR A PLASTIC BAG),WHICH DOES NOT CONTAIN ANY TRACES OF SOAP OR DESINFECTANT SUBSTANCES. DO NOT USE STOOLS CONTAMINATED WITH WATER, URINE OR TOILET PAPER.
2. UNSCREW THE TOP OF THE CONTAINER WITH LIQUID INSIDE. THROW THE TOP OUT.
3. USE THE SPADE ALONG WITH THE CONICAL TUBE TO TAKE A STOOL SAMPLE SMALLER THAN THE SIZE OF A PEA, PREFERABLY FROM AREAS SHOWING BLOOD OR LIQUIDS. REMEMBER THAT TE SAMPLE MUST BE SMALLER THAN THE SIZE OF A PEA.
4. PUT THE SPADE INTO THE CONTAINER WITH LIQUID INSIDE AND SCREW IT IN FIRMLY.SHAKE IT GENTLY WITHOUT INVERTING IT.
KEEP THE CONTAINER AT ROOM TEMPERATURE (DO NOT KEEP IT IN THE FRIDGE) WITH THE CONICAL END POINTING UP,UNTIL THE SAMPLE IS TAKEN TO THE LABORTORY OR THE HEALTH CENTRE.
5. WASH YOUR HANDS THOROUGHLY WITH WATER AND SOAP.

DO NOT INGEST THE LIQUID CONTENT OF THE CONTAINER.

ATTENTION!

THE LIQUID CONTENT OF THE CONTAINERS IS TOXIC.

KEEP IT AWAY FROM CHILDREN

IN CASE OF AN ACCIDENTAL INTAKE, DRINK A BIG AMOUNT OF MILK OR WATER AND CONSULT A MEDICAL SERVICE IMMEDIATELY.

IF THE LIQUID CONTENT COMES INTO CONTACT WITH SKIN, EYES AND MUCOUS, WASH THOROUGHLY.